

FlamMap Installation Instructions

NOTE: If you have created custom legends or color ramps or you would like to retain your history of landscape requests using *Get Landscape*, review page 2.

Forest Service: Should be able to install from any location on your computer.

DOI: FlamMap is approved for every DOI bureau. Please go through your normal process for software installation.

1. Uninstall FlamMap if it is currently installed on your computer.
 - Settings>Apps>Installed apps
 - Find the old version of FlamMap, select the three dots on the right, and select "Uninstall".
2. Download the installation zip file to a location on your computer (e.g., C:\Downloads\) and extract the files.
3. The default installation location (**C:\ProgramFiles\FlamMap6**) is recommended. Double-click *FlamMap_Setup.exe*, click "Next" on the three installation screens and click "Close" to finish the installation.

Installation Tips:

- **FlamMap MUST be installed using the FlamMap_Setup.exe file**
- **Install FlamMap to Default location: at C:\ProgramFiles\FlamMap6**
 - If you choose to install the program in a Different location it must be to an area with full Read/Write Access as FlamMap requires an area that it can write and store temporary files to.
- FlamMap is a fire analysis desktop application that ONLY runs in a 64-bit Windows Operating System environment.
- DO NOT install the program on a server location that will be accessed across a network.
- DO NOT install in Program Files (x86)
- DO NOT install on Desktop [creates long pathname issues]
- DO NOT install in My Documents [creates long pathname issues]

Once installed you can create a Desktop shortcut.

FILES YOU MIGHT WANT TO SAVE PRIOR TO UNINSTALLING

Three files should be copied and saved from the users current FlamMap installation folder (typically, C:\Workspace\FlamMap6) prior to uninstalling the current version of FlamMap6.

Prior to uninstalling current FlamMap6 installation, copy the following three files from the current FlamMap6 installation directory.

1. "**FlamMap6.cfg**" -- This config file (.CFG) includes custom legends or color ramps the user has created.
2. "**layouts.json**" -- This file contains table and dialog layouts.
3. "**GetLandscapeHistory.xml**" -- This file has the history of landscape requests the user has made.

After installing the new version of FlamMap:

- Place the "**FlamMap6.cfg**" and "**layouts.json**" files in this location:
C:\Users\"Username"\AppData\Local\FlamMap6
- Place the "**GetLandscapeHistory.xml**" file in this location:
C:\Users\"Username"\AppData\Local\GetLandscape